

# KeySoft Release notes April 2022 update

## KeyWord V13.0

- Open and save documents to Google Drive and other cloud storage
- Navigate using webview elements when previewing a document
  - o Press **Enter + V** to display the preview.
- Fixed the issue where Arabic text was not being shown visually in preview.
- Printing procedure has been simplified.
  - o A print button is available in the preview mode.
- Jump to the save edit box when navigating within the KeyFiles (Space + S)

## KeyBRF V11.0

Update to allow access to Google Drive cloud storage.

## KeyCalc v11.0

- Updated Duxbury Braille Library
- Fixed crash in KeyCalc

## KeyFiles V11.0

- Refactored KeyFiles to allow access to Google Drive and other cloud storage.
- Limitation on copying to OneDrive
  - o OneDrive will not be visible when copying is evoked.
- Limitation on opening and saving files within Dropbox
  - o When saving an existing file Dropbox will create a new copy.
- Replaced the Paste shortcut with an action shortcut (Backspace + A)
- Where am I (Space + dots 1+5+6) gives you the current location in dropdown list
- Documents and Download folder pinned to the storage selection

## KeyMath V10.0

- New Duxbury Braille Library
- Fixed math symbols not represented properly.
- Fixed some expressions to accept a wider variety of parameters.

## KeyMail V13.0

- Fixed the issue where you are prompted with an error page when trying to setup an account using Google Sign in.
- Update to allow access to Google Drive cloud storage.

## KeySlides V1.0

- A new KeySoft PowerPoint file reader application
  - o Next Slide = Enter with O
  - o Previous Slide = Enter with dots 2,4,6
  - o Index = Enter + I
  - o Toggle between notes and slide = Space + N
  - o Go to slide from the index view = Enter + G

## New Language braille tables

- Added Spanish, French and German Braille tables to follow Method 2 (UKAAF) and Method 3 (BANA)
  - o UEB required for punctuations. Grade 1 letters.

## KeySoft Release notes April 2022 update

- Native accents required. (Not UEB)

### KeySoft & Braille Manager:

- Updated Duxbury Braille Library
- Improved accessibility to Google Docs and Kindle App.
  - Introduced braille shortcuts within Google Docs, subject to break on Google's update. List of shortcuts are available on the HumanWare support page.
  - Turn over the page within Kindle by pressing Enter + O or previous page Enter with dots 2,4,6. Can also use Next and left thumb key or Previous and Right thumb key.

### KeyUpdater V10:

- A two pass update is required install this version.
  - First update will update KeyUpdater Only
  - A second update is required to install this version.

### Easy Reader:

- New Library added : Calibre Audio (UK)
- Updated Library: Blind Low Vision (NZ) Two new categories added "Books" and "Magazines"
- Various fixes including where Audio speed was not working in some books.